



life.augmented

# Liquid Level Monitoring using the L4CD example with STM32CubeIDE



# Prerequisites

- Software's
  - For embedded software development
    - STM32CubeIDE : <https://www.st.com/en/development-tools/stm32cubeide.html>
  - For PC development
    - Python 3.6 or newer
    - PyQt5 component
  - No prerequisite SW for simple evaluation with the .exe GUI tool
- Assumption
  - The example project is unzipped in the following directory : C:\STSW-IMG039\_L4CD
- Ensure that the full experiment is ready
  - P-Nucleo VL53L4A1 package connected to your PC through the USB from [st.com](https://www.st.com)



# Characterization of the container

- Done from the C:\STSW-IMG039\_L4CD\VL53L4CD\_GUI\_Nonlinearity Algorithm directory
- The characterization can be done using
  - the .exe GUI
  - the python version of the GUI
- Before using the GUI, the *config.txt* file needs to be updated.


```
config.txt ✖ |
1  firmware=VL53L4
2  OCalgorithm=0
3  totalheight=200
4  offsetcalibration=100
5  indicators=5
6  characterization=2
7  turbu_det_std=20
```

Field	Description
firmware	Name of the Firmware/Product Example: VL53L4
OCalgorithm	Enable the nonlinearity correction algorithm. Enable:1, Disable:0
totalheight	Distance between the sensor and the bottom of the container in mm Example: 200mm
offsetcalibration	Height to do the calibration procedure as per the recommendation of the datasheet of the product. Recommended: 100mm distance to the liquid from top of the sensor
indicators	Number of steps to measure liquid Example: 5
characterization	Number of the rerun to characterize the container Example: 2
turbu_det_std	Standard deviation to be considered over 5 consecutive measurements to check if there is a turbulence. Example: 20



# Characterization of the container using the .exe GUI file


- Launch the GUI available in the *GUI Nonlinearity Algorithm* directory :  
GUILiquidLevel.exe





# Characterization of the container using the .py file

- The following Classes and Methods are defined for the py GUI
  - **class** CharacterizationPlot() : It draws each characterization, regression and offset data point in line plot.
    - **def** regression\_plot(): it plots regression line based on all data points
    - **def** OffsetGainAlgo(): It plots offset gain line based on all data points
  - **class** Liquidmeasuredemo(): Main GUI window, and all layout control from here.
    - **def** read\_config(self):- read configuration file
    - **def** update\_plot(self, obj): Update liquid level based on received distance from port
    - **def** OGalgorithm\_range(self,range): Find liquid level position and apply offset on ranging
  - **class** LiquidMeasPlot(QWidget): Create Liquid level Tank
    - **def** paintEvent() : Liquid level control display
- Open in PyCharm and run  
GUILiquidLevel.py with Python 3.6 or newer






# Characterization of the container

- Step-1: Flash Firmware (Soft Reset board)
  - Click “FlashFW” to flash the firmware to Nucleo board
- Step-2: Perform Offset Calibration (as per datasheet recommendation)
  - Pour “Liquid/Water” up to 10 cm distance from sensor
  - Click Off+Xtalk calibration method
- Step-3: Remove liquid from the container
- Step-4: Perform Characterization
  - a. Pour “Liquid/Water” up to the first indicator level
  - b. Click “Characterization”

Perform again steps 4a and 4b until the characterization is done for all the levels.

All the results are logged in the FinalResults.csv and characterization.txt file


- Example: in the config.txt file, “characterization”=4 and indicators =10
  - Final results would be produced after 36 iterations.
  - Note: Last step (100%) is not considered as practically not useful






# Additional Features of the characterization GUI 1/2

The message “Misplaced Sensor Position” pops up when the ranging distance crossed the height of the container. In this case, the sensor is assumed to be misplaced.




This message “Liquid Overflow” pops up when the ranging distance is equal to the height of the container. This means the container is full of liquid. In this example: total distance is 210mm






# Additional Features of the characterization GUI 2/2

The message “Detect Turbulence” pops up when the standard deviation over 5 consecutive measurements is greater than `turbu_det_sdt` variable defined in the `config.txt` file. Depending on the value of the standard deviation, small or big turbulence can be detected.





# Outputs of the characterization tool : Graph



In the below plot, the characterization has been done 4 times with the same setup and the OCalgorithm has been enabled.





# Outputs of the characterization tool : files

- 3 files are generated :
  - Finalresults.csv
    - Table with datas stored during the characterization phasis

	Expecte dRes	Liquidlev el	4_iter_dev	3_iter_dev	2_iter_dev	Mean_dev	OG_val	Offalgo_pred
C9	21	90	5	3	7	5	4	27
C8	42	80	3	4	2	3	4	44
C7	63	70	1	1	1	1	2	64
C6	84	60	3	1	3	2.3	1.6	88
C5	105	50	7	6	9	7.3	4.8	109.1
C4	126	40	19	19	21	19.6	13.5	133.5
C3	147	30	29	27	34	30	24.8	152.1
C2	168	20	30	29	31	30	30	169
C1	189	10	11	3	18	10.6	20.3	172

Indicator level      Expected Result(mm)      Liquid level (%)      Deviation calculate in each iteration      Mean deviation      Offset compensation      Final Predication



Characterization Data

- OffGainVal.csv
  - Lookup table to be stored in the host memory to improve the ranging accuracy

Indic ator level	Expect edRes	OG_ val
C9	21	4
C8	42	4
C7	63	2
C6	84	1.6
C5	105	4.8
C4	126	13.5
C3	147	24.8
C2	168	30
C1	189	20.3

Indicator level      Expected Result(mm)      Offset compensation

- Characterization.txt
  - Datapoints of all iterations

{4: [26.0, 45.0, 64.0, 87.0, 112.0, 145.0, 176.0, 198.0, 178.0],3: [24.0, 46.0, 64.0, 85.0, 111.0, 145.0, 174.0, 197.0, 186.0],  
2: [28.0, 44.0, 64.0, 87.0, 114.0, 147.0, 181.0, 199.0, 171.0], 1: [27.0, 44.0, 64.0, 88.0, 114.0, 147.0, 177.0, 199.0, 172.0]}





# Ranging

- Once the container is characterized, there are two solutions for ranging :
  - Continue to use the GUI for single ranging by clicking on the *Ranging* button
  - Use STM32CubeIDE for embedded software development
    - Before ranging using the STM32CubeIDE, some code modifications must be done in the main.c like the compensation look-up table, the height of the container, etc.... Next four slides explain the process to follow.



# Ranging with STM32CubeIDE 1/4

- Launch STM32CubeIDE
  - An *Information Center* window will open – You can close it or leave it open.
- Create a workspace to compile and run your project
  - File / Switch Workspace / Other  
*For this example, we will create a workspace called VL53L4CD\_LLM\_workspace in the STSW-IMG039\_L4CD/VL53L4CD\_LevelMonitoring\_CubeIDE*
- Import the project .ioc delivered
  - File / Import / General / Projects from Folder or Archive






# Ranging with STM32CubeIDE 2/4

- Import the project from the following directory :

C:\STSW-IMG039\_L4CD\VL53L4CD\_LevelMonitoring\_CubeIDE\LiquidLevel\_VL53L4CD\_F401RE

You will have to check the box :

CubeIDE\_F401RE\_Example if not done



- Before ranging, the *ogalgo\_data* structure of the main.c file must be updated with the lookup table generated during the characterization in the OffGainVal.csv file

- Example :


```
/*Start: Measure liquid level application*/
/*Consider X indicator levels and define a structure to store level, expected result and compensation value*/
#define MAX_LABEL 10 /* Number of level indicators - To be updated depending on the number of the level in the OffGainVal.csv file */
typedef struct ogalgo_data
{
    uint8_t level ;
    uint16_t expected_res;
    uint16_t og_val;
}ogalgo_data;
```

```
/* Design a lookup table with a structure compensate value data received from GUI once characterization is done */
/* First column : indicator level , Second column: Expected result , Third Column: compensate value */
/* hardcoded , NEED to BE CHANGED */
ogalgo_data ogalgo_data_inst[MAX_LABEL]={
{ 9, 21, 4 },
{ 8, 42, 4 },
{ 7, 63, 2 },
{ 6, 84, 1 },
{ 5, 105, 5 },
{ 4, 126, 14 },
{ 3, 147, 25 },
{ 2, 168, 30 },
{ 1, 189, 20 },
};
uint8_t algo_enable=1; /* algo_enable=1 to apply the lookup table - algo_enable=0 to not apply */
uint16_t totaldistance=270; /* in mm - Height between the sensor and the bottom of the container */
uint16_t meanranging=0;
uint16_t rangevalue_out=0;
uint16_t invalid_range=999;
/* End: Measure liquid level application */
```




# Ranging with STM32CubeIDE 3/4

- Build the project using the hammer tool



- In the console window you should have no error at the end





# Ranging with STM32CubeIDE 4/4

- Launch a serial com port tool like Putty or Tera Term
- Configure the serial port settings as :  
*Choose the right COM port and set the speed to 115200*
- You will have the following reported in the Tera Term window
- If nothing is return in the Tera Term VT window, you may need to press the black reset button on the NUCLEO board

